

ExportCKDfiles program for KeyCreator 9.X only!

Use this program at your own risk!

Program description:

This program allows the multiple selections of multiple CKD files, adds them to a list and then exports all of the selected files to the various export types available in KeyCreator without user interaction. The CKD files are saved with their native name with the appropriate extensions of the selected file types. Like SprinklerAssembly.ckd would be exported as SprinklerAssembly.pdf if PDF was selected as an export type.


There is some special file naming going on, when exporting certain types, like PDF & PDF3D. Since both files have the pdf extension, I add 3D to the CKD name, like SprinklerAssembly 3D.pdf, if the PDF3D type is selected for export.

The export can be interrupted by the user by pressing the ESC key on the keyboard.

All settings are remembered unless the Close button is pressed.

All export settings for the various types are whatever is set in KeyCreator, except for DXF & DWG export, they may be adjusted in the program.

The ExportCKDfiles Dialog Box



Here is some additional help; items that are self explanatory are not listed.

Export Folder Options:

Export Folder Options

Export files to directory of original file

Export files to a single directory

C:\KeyCreator8.5\image

Create a Error log file on disk during translation

C:\KeyCreator8.5\KXL\ExportErrorLog.txt

The first text box is the place where the exported files end up. Either by the directory specified, as shown, or in the directory of the original file.

The second text box is the place to enter a file name & path (optional) to store error information of the export that might have occurred.

You have to make sure that the path in either text box exists; otherwise the output directory is unpredictable.

File types to be exported:

File Types to be exported

SAT	<input type="checkbox"/> Yes	X_T	<input type="checkbox"/> Yes
SAB	<input type="checkbox"/> Yes	X_B	<input type="checkbox"/> Yes
IGES	<input type="checkbox"/> Yes	DWG	<input type="checkbox"/> Yes
STEP	<input type="checkbox"/> Yes	DXF	<input type="checkbox"/> Yes
STL	<input type="checkbox"/> Yes	HMF	<input type="checkbox"/> Yes
PDF	<input checked="" type="checkbox"/> Yes	H5F	<input type="checkbox"/> Yes
PDF3D	<input type="checkbox"/> Yes	HTML	<input type="checkbox"/> Yes
HPGL	<input type="checkbox"/> Yes	BMP	<input checked="" type="checkbox"/> Yes
HPGL2	<input type="checkbox"/> Yes	DIB	<input checked="" type="checkbox"/> Yes
CGM	<input type="checkbox"/> Yes	GIF	<input checked="" type="checkbox"/> Yes
CGM3	<input type="checkbox"/> Yes	JPG	<input checked="" type="checkbox"/> Yes
OBJ	<input type="checkbox"/> Yes	TIF	<input checked="" type="checkbox"/> Yes
U3D	<input type="checkbox"/> Yes		

Catiav4Model Yes

Catiav4Export Yes

Catiav4Session Yes


Catiav5Part Yes

Export Layouts for type

PDF, BMP, DIB
GIF, JPG, TIF


You may select as many file types as you want. Some export options allow layouts to be exported as well, shown in the *Export Layouts for type* option box. If this option is selected, then all layouts in a file will be exported. If a layout is exported the layout name is added to the original CKD filename. Should no layout name exist, then the layout number is added to the original CKD filename.

List of files to be exported:




The list pane keeps track of all the CKD files in the selection list. Pressing the Clear CKD List button will erase all previously selected files.

DXF/DWG Settings:



These are all the regular KeyCreator DXF/DWG export settings. Please be advised that the two options “*convert all layouts to paperspace in same file*” and “*convert each layout to 2D model space in separate files*” are switched from the standard KeyCreator DXF/DWG option dialog. The reason is, that these two commands are ordered this way in the KXL command structure.

Select CKD Files:



Pressing this button opens the Open Dialog Box to select files. You may select as many CKD files as you want. You are allowed to press this button multiple times exploring different directories where CKD files are stored. When the Open Dialog Box is displayed you may press the Ctrl or Shift key for multiple file selections.

CKD Names stored in File:

CKD Names stored in File

You may point to a single file, containing CKD filenames in an organized manner, like

C:\KeyCreator\ckd\test.ckd

C:\KeyCreator\ckd\Sprinkler.ckd

C:\KeyCreator\ckd\Arm.ckd

C:\KeyCreator\ckd\Heatshield.ckd

All data is added to the list pane

Export CKD List:

Export CKD List

Once all selections are made, press this button to export all data.

Upon completion of session:

When no errors occurred the following dialog box will be displayed.



If there were errors, then this dialog box will be displayed



The user may then press yes to view the export errors, or No not to view them.